



Interfacing

Trim 1/2"(13mm) from seam allowances of INTERFACING section. Fuse to wrong side of matching FABRIC section, following manufacturer's instructions.



Crown and Top



STAY STITCH upper curved edge of CROWN 1, as shown.



Stitch ends of crown together at center back.




With right sides together, pin TOP 2 to crown, matching centers and symbols, clipping crown where necessary. Stitch. Stitch again 1/4"(6 mm) away in seam allowance. Trim close to second stitching. Press seam toward crown.




Brim


Stitch ends of each BRIM 3 section together at center back.




Pin brim sections together, matching centers, seams and symbols. Stitch, leaving inner edge open. Trim and clip seam.




Turn. Press. Baste raw edges together.




STAYSTITCH inner curved edge of brim.



View A: Pin brim to crown, matching centers and symbols, clipping brim where necessary. Baste.




View B: With matching fabric sides together, pin brim to crown, matching centers and symbols, clipping brim where necessary. Baste.




All Views:

On inside, pin grosgrain ribbon to brim seam allowance, placing lower edge along seamline, turning in 1/4"(6mm) on each end to meet at center back, as shown. Stitch ribbon in place along seamline. Trim, being careful not to cut ribbon.




Turn ribbon toward crown along seam; press. To form casing, stitch along upper edge of ribbon, as shown.




Cut elastic the measurement of head plus 1"(25mm)


Insert elastic through opening in casing, lapping ends 1"(25mm); hold with safety pin. Try on and adjust if necessary. Stitch ends of elastic securely.



SLIP STITCH opening in casing.




Tack brim to crown at center front, matching 's, as shown.




Flower


Stitch FLOWER 4 sections together along notched edges, as shown.




With wrong sides together, fold flower along foldline. Baste raw edges together along 1/4"(6mm) seamline. Press lightly.




To gather, stitch along 1/4"(6mm)seamline, with heavy thread, using long machine stitches.



Adjust gathers tightly. Knot ends of thread securely, as shown.



To form flower, starting at one end, roll flower toward you, securing layers with heavy thread as you roll. Sew edges together.




Sew STAY 5 section along 1/4"(6mm) seamline by hand, using long stitches.





Draw thread on stay, turning in outer edge, as shown. Baste. Press, easing in fullness.



Center stay over bottom of flower. **SLIP-STITCH** basted edge along gathering stitches on flower.



Center stay of flower over • on brim, as shown. Sew stay invisibly and securely in place.



Open flowers to desired fullness, as shown.